

# Backup Exec Utility

---

This section includes the following topics:

- [About Backup Exec Utility](#)
- [Starting the Backup Exec Utility](#)
- [About Backup Exec Utility general tasks](#)
- [About Backup Exec Utility services tasks](#)
- [About Backup Exec Utility CASO tasks](#)
- [About Backup Exec Utility database tasks](#)
- [About Backup Exec server group tasks](#)
- [About configuring columns](#)

## About Backup Exec Utility

Use the Backup Exec Utility, `beutility.exe`, to perform various configuration. It is installed in your Backup Exec working directory during the initial Backup Exec installation.

With the Backup Exec Utility, you can do the following tasks:

- Add, remove, and configure logical groups of Backup Exec servers. With logical groups, you can perform operations on all of the computers in a group at the same time. These operations include starting or stopping services and configuring application service security, such as changing service account information. You can also use the Backup Exec Utility to configure startup options for one or more of the servers in a group.
- Start immediate database utility operations on the Backup Exec Database (BEDB). The database maintenance utilities usually initiate these utilities. You can start database dumps and run database consistency and data integrity checks.

“ ”

**Note:** You should use the Backup Exec Utility only with the guidance of Technical Support. Improper use of this utility can result in configuration changes that may prevent Backup Exec from running.



More Information

[Starting the Backup Exec Utility](#)

[About Backup Exec Utility general tasks](#)

[About Backup Exec Utility CASO tasks](#)

[About Backup Exec Utility services tasks](#)

[About Backup Exec Utility database tasks](#)

[About Backup Exec server group tasks](#)

## Starting the Backup Exec Utility

The beutility.exe file is located in the main program directory.

`< Backup Exec install path > \Backup Exec\`

After you start Backup Exec Utility, you should add a Backup Exec server.

See [Adding Backup Exec servers](#).

To start the Backup Exec Utility

- From the Backup Exec main program directory, double-click **beutility.exe**.

## About Backup Exec Utility general tasks

Table: [Backup Exec Utility general tasks](#) lists the Backup Exec Utility general tasks.

Table: Backup Exec Utility general tasks

TASK	DESCRIPTION
<a href="#">Adding Backup Exec servers</a>	Adds a Backup Exec server to Backup Exec Utility's list of known Backup Exec servers.

TASK	DESCRIPTION
Adding a new Agent for Windows computer	Adds a computer that runs the Agent for Windows to the All Agent for Windows Computers node.
Viewing server properties for the Agent for Windows computer	Displays the server properties for an Agent for Windows computer.
Viewing system properties for the Agent for Windows computer	Displays the system properties for an Agent for Windows computer.
Creating a new Backup Exec server group	Creates a container where you can logically group together multiple Backup Exec servers.
Deleting a Backup Exec server from the Backup Exec Utility list of known Backup Exec servers	Removes Backup Exec servers from the Backup Exec Utility list of known servers.
Deleting a computer on which the Agent for Windows is installed	Deletes an Agent for Windows computer.
Deleting a Backup Exec server group	Removes user-defined Backup Exec server groups from the Backup Exec Server Groups node.
Running Backup Exec diagnostics	Runs the Backup Exec Diagnostics application on the Backup Exec servers that are listed in the Backup Exec Utility.
Enabling debug logs	Activates logs for a variety of Backup Exec engine-related debugging activities.
Setting the size of the debug logs	Sets the size of the debug log files.
Setting debug logging and the debug log sizes for Agent for Windows computers	Activates and configures various options for log file operations on computers running the Agent for Windows.
Setting the location for the job log and the catalogs	Sets the hard disk location for the job log and the catalogs.

TASK	DESCRIPTION
Viewing server properties for the Backup Exec server	Displays server properties for any Backup Exec server that appears in Backup Exec Utility.
Viewing a list of licensed and installed options for a Backup Exec server	Displays a list of installed options for any Backup Exec server that appears in Backup Exec Utility.
Viewing system properties for a Backup Exec server	Displays system properties for any Backup Exec server that appears in Backup Exec Utility.
Managing security certificates	Displays the security certificates for the Backup Exec server.

## Adding Backup Exec servers

Before you can reconfigure or modify Backup Exec servers, you must add the names of the Backup Exec servers in the Backup Exec Utility.

See [About Backup Exec Utility general tasks](#).

To add Backup Exec servers

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the task pane, under General Tasks, click **New Backup Exec server**.
3. Select the options that you want to use to add a Backup Exec server.

See [Select Backup Exec server options](#).

1. Click **OK**.

### Select Backup Exec server options

Select the options you want to use to add a new Backup Exec server.

See [Adding Backup Exec servers](#).

**Table: Select Backup Exec server options**

ITEM	DESCRIPTION
Backup Exec Server	Indicates the name of a Backup Exec server that you want to add.
	You can also click Browse to find a Backup Exec server to add.
Check Backup Exec Server status	Validates that the Backup Exec server is a Backup Exec server before it is added to the Backup Exec Utility list of Backup Exec servers.
Include all Backup Exec Servers known by this Backup Exec Server	Adds other Backup Exec servers that may be part of a CASO environment to the Backup Exec Utility list of servers.
Get Server Information	Displays the properties of the Backup Exec server that appears in the Backup Exec server field.

## Adding a new Agent for Windows computer

New Agent for Windows Computer lets you add a computer running the Agent for Windows to All Agent for Windows Computers.

To add a new computer running the Backup Exec Agent for Windows

1. In the Computers pane, expand Known Computers.
2. Click **All Agent for Windows Computers**.
3. In the task pane, under General Tasks, click **New Agent for Windows Computer**.
4. Type the name of a computer running the Backup Exec Agent for Windows, or click **Browse** to navigate to the computer.
5. Click **OK**.

## Viewing server properties for the Agent for Windows computer

You can view the following server properties:

- Name

- Status
- Version
- Description

To view server properties for the Agent for Windows computer

1. In the Computers pane, under Known Computers, click **All Agent for Windows Computers**.
2. In the results pane, right-click a computer.
3. Click **Agent for Windows Computer Properties**.
4. Click the Server tab.

See [Server properties for the Agent for Windows computer](#).

1. Click **OK**.

### Server properties for the Agent for Windows computer

The Server tab provides the following information.

See [Viewing server properties for the Agent for Windows computer](#).

**Table: Server properties for the Agent for Windows computer**

ITEM	DESCRIPTION
Name	Displays the name of the computer running the Agent for Windows.
Status	Displays the status of the computer running the Agent for Windows.
Version	Displays the Backup Exec Agent for Windows version and revision number.
Description	Displays a description of the computer running the Agent for Windows.

### Viewing system properties for the Agent for Windows computer

You can view information about the operating system and processor. In addition, you can run the BE Diagnostics utility.

To view system properties for the Agent for Windows computer

1. In the Computers pane, under Known Computers, click **All Agent for Windows Computers**.
2. In the results pane, right-click a computer.
3. Click **Agent for Windows Computer Properties**.
4. Click the System tab.

See [System properties for the Agent for Windows computer](#).

1. Click **OK**.

### System properties for the Agent for Windows computer

The System tab provides the following information.

See [Viewing system properties for the Agent for Windows computer](#).

**Table: System properties for the Agent for Windows computer**

ITEM	DESCRIPTION
Type	Displays the type of operating system that is installed on the computer.
Version	Displays the version of the operating system.
Build	Displays the build number of the operating system.
Type	Displays the type of processor that is installed in the computer.
Level	Displays the level of the processor that is installed. For example, Pentium IV.
Number of processors	Displays the number of processors on the computer.
BE Diagnostics	Runs the BE Diagnostics utility.
	The results are written to a text file that is called bediag.txt.
	The text file contains the following configuration information:

ITEM	DESCRIPTION
	- Account groups, account privileges, and environment settings.
	- Backup Exec software version and registry information, Backup Exec Agent listing, and Windows version information. The text file also provides SCSI hardware configuration, SQL Server information, Driver services information, and Windows Services information.
	- File server information, supported shared directories, and Windows sockets information.
	If you call technical support, they may request that you run BE Diagnostics and provide them with the results. Technical Support can use the results of this utility to pinpoint your problem and quickly solve it.

## Creating a new Backup Exec server group

New Backup Exec Server Group lets you create a container where you can logically group together multiple Backup Exec servers. After you create a group, you can add Backup Exec servers to it by using the Add Server task.

When you add Backup Exec servers to a group, you can perform operations on the entire group at the same time.

“ ”

**Note:** Do not place Backup Exec cluster nodes in the same Backup Exec server Group as the virtual Backup Exec server. If a function runs on a Backup Exec server Group that contains cluster nodes and contains the virtual Backup Exec server, Backup Exec Utility has problems when it tries to modify the virtual Backup Exec server.

“ ”

To create a new Backup Exec server group

1. In the Computers pane, click **Backup Exec Server Groups**.
2. In the task pane, under General Tasks, click **New Backup Exec Server Group**.
3. Enter the appropriate details to create a new Backup Exec server group.

See [New Backup Exec server group options](#).

1. Click **OK**.

More Information

[Adding a Backup Exec server to a Backup Exec server group](#)

### New Backup Exec server group options

Complete the following options to create a new Backup Exec server group.

See [Creating a new Backup Exec server group](#).

**Table: New Backup Exec server group options**

ITEM	DESCRIPTION
Backup Exec server group	Indicates the name of a Backup Exec server group.
Create group from CASO configuration	Lets you create a Backup Exec server group from the computers that comprise a CASO configuration.
Central administration server	Indicates the name of the central administration server.

### Deleting a Backup Exec server from the Backup Exec Utility list of known Backup Exec servers

Delete Backup Exec server lets you remove Backup Exec servers from the Backup Exec Utility master list of known servers. Backup Exec servers that are on the master list appear in All Backup Exec Servers. Deleting a Backup Exec server from All Backup Exec Servers does not affect the operational status of the Backup Exec server.

You cannot use Delete Backup Exec Server to remove Backup Exec servers from Backup Exec Server Groups.

To delete a Backup Exec server from the Backup Exec Utility list of known Backup Exec servers

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the task pane, under General Tasks, click **Delete Backup Exec Server**.
3. Select a Backup Exec server to delete.

More Information

[Removing a Backup Exec server from a Backup Exec server group](#)

## Deleting a computer on which the Agent for Windows is installed

Delete Agent for Windows Computer lets you delete the computers that are running the Agent for Windows from All Agent for Windows Computers. Using this option does not uninstall the Agent for Windows from the computer.

To delete a computer on which the Agent for Windows is installed

1. In the Computers pane, click **All Agent for Windows Computers**.
2. In the task pane, under General Tasks, click **Delete Agent for Windows Computer**.
3. Select a computer to delete.
4. Click **OK**.

## Deleting a Backup Exec server group

Delete Backup Exec Server Group lets you remove user-defined Backup Exec server groups from Backup Exec Server Groups.

All Backup Exec servers that are contained in the Backup Exec server group are deleted along with the Backup Exec server group itself. Although they are deleted from the group, the deleted Backup Exec servers are not removed from All Backup Exec Servers.

To delete a Backup Exec server group

1. In the Computers pane, click **Backup Exec Server Groups**.
2. In the task pane, under General Tasks, click **Delete Backup Exec Server Group**.
3. Select a Backup Exec server group or groups to delete.

See [Delete Backup Exec Server Group](#).

1. Click **OK**.

## Delete Backup Exec Server Group

Delete Backup Exec Server Group displays an existing list of Backup Exec server groups that you can delete from Backup Exec Server Groups.

“ ”

**Note:** All Backup Exec servers that are contained in the Backup Exec server group are deleted along with the Backup Exec server group itself. Although they are deleted from the group, the deleted Backup Exec servers are not removed from All Backup Exec Servers.

“ ”

More Information

[Deleting a Backup Exec server group](#)

## Running Backup Exec diagnostics

BE Diagnostics starts the Backup Exec Diagnostics application on the Backup Exec servers that appear in the Backup Exec Utility.

Backup Exec Diagnostics gathers information about Windows computers for troubleshooting purposes. You can find this application in the Backup Exec directory on your hard drive. The default location of the Backup Exec Diagnostics application is `<Backup Exec install path>\Backup Exec\`.

To run BE Diagnostics

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the results pane, select a Backup Exec server.
3. In the task pane, under General Tasks, click **BE Diagnostics**.

BE Diagnostics sends its output to an ASCII text file called bediag.txt. You can find this text file in the default Backup Exec installation directory:

```
<Backup Exec install path>\Backup Exec\
```

## Enabling debug logs

### Enabling debug logs

Enable Debug Logs lets you activate Backup Exec debug routines for a variety of Backup Exec services. In addition, Enable Debug Logs also creates debug log files that are stored on a Backup Exec server hard drive.

You should only use Enable Debug Logs when Technical Support needs specific information about your Backup Exec installation. Activating debug logging greatly affects Backup Exec server performance.

In a default installation, Backup Exec log files reside in the Logs directory, in the following path:

```
< Backup Exec install path > \Backup Exec \Logs
```

If you install Backup Exec to a different path, use that path instead.

To use the Enable debug logs task

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under General Tasks, click **Enable Debug Logs**.
3. Set the appropriate options.

See [Enable debug log configuration options](#).

1. Complete the debug log configuration options as directed by technical support.

### Enable debug log configuration options

Complete the following options as directed by technical support.

See [Enabling debug logs](#).

**Table: Enable debug log configuration options**

ITEM	DESCRIPTION
Backup Exec Server	Displays the name of the Backup Exec server.
Enable debug log for Server service	Lets you set debug logging and log levels for the Backup Exec Server service.

ITEM	DESCRIPTION
Debug detail level	Sets the level of detail that you want in the debug log files.
	Choices include Normal, Medium, High, and Max.
	Technical support determines the level to use.
Basic log (includes clients, server calls, and VSNS)	Activates the Backup Exec log.
SQL log	Sets the level of detail in the SQL logs.
	Two levels are available: Low and High.
	Technical support determines the level to use.
Job log	Sets the level of detail in the job logs.
	Two levels are available: Low and High.
	Technical support determines the level to use.
Message log	Activates the log that is required to debug the Backup Exec messaging system.
Performance log	Activates the log that is required to debug BEServer service performance issues.
Enable debug log for message queue	Activates the log that is required to debug the Backup Exec message queue service.
Enable debug log for Job Engine and Remote Agent for Windows service	Activates the log that is required to debug both the Backup Exec Job Engine and Remote Agent for Windows services.
Engine NDMP debug level	Sets the level of Engine NDMP debugging details that are logged.
	Technical support determines the level to use.

ITEM	DESCRIPTION
Log NDMP errors only	Provides both general information and the errors that are generated.
Log flow messages	Provides additional information about the activity that is occurring and the NDMP errors that are generated.
Verbose Logging	Provides additional information that you do not get with either of the Log NDMP errors only or Log flow messages options.
NDMP Option debug level	Lets you set the level of Agent for Windows debugging details that are logged.
	Technical support determines the level to use.
Log NDMP errors only	Provides both general information and the errors that are generated.
Log flow messages	Provides additional information about the activity that is occurring and the NDMP errors that are generated.
Verbose Logging	Provides additional information that you do not get with either Log NDMP errors only or Log flow messages options.
Log file append	Appends engine and remote agent NDMP log information to the existing engine and remote agent NDMP log file.
Enable debug log for Notification services	Lets you configure the log that is required to debug the Backup Exec Notification services.
Backup Exec server	Activates the notification logging on a Backup Exec server running the Backup Exec BESERVER service. This option should only be used with guidance from technical support.
Administration console	Activates the notification logging on a computer running the Backup Exec Administration Console. This option should

ITEM	DESCRIPTION
	only be used with guidance from technical support.
Enable debug log for Catalog	Lets you set the level of logging that is required to debug the Backup Exec catalogs.
Debug level	Multiple levels of debugging details are available.
	Debug levels include the following:
	- Error only Provides error message information only.
	- Performance Provides performance information on Backup Exec catalog operations in milliseconds.
	- Normal Provides a normal level of debug log information.
	- Detail Provides more verbose log information.
	- Dump memory Provides more verbose logging details by dumping the contents of the memory buffer for catalog debug analysis.
	Technical support determines the level to use.

## Setting the size of the debug logs

Set Debug Log Size and Location lets you set the maximum size of the log files that are generated for the following Backup Exec services:

- Backup Exec Server
- Backup Exec Job Engine
- Backup Exec Remote Agent for Windows

You can also set the location of the debug log files.

To set the debug log size

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under General Tasks, click **Set Debug Log Size and Location**.
3. Set the options as appropriate.

See [Set debug log size options](#).

1. Click **OK**.

### Set debug log size options

You can set the following options as directed by technical support.

See [Setting the size of the debug logs](#).

**Table: Set debug log size options**

ITEM	DESCRIPTION
Backup Exec Server	Displays the name of the Backup Exec server for which you want to change debug log sizes.
Enable log size for BEServer	Lets you set log details for BEServer.
Log size limit mode	Determines the options to take when the log file for the Backup Exec Server service reaches its maximum size.
	The following choices are available:
	- Rename when the maximum size is reached
	- Max retention
	On selecting the Rename when the maximum size is reached option, when the Backup Exec server log file, <code>log_beserver.txt</code> , reaches the specified individual file size, Backup Exec server renames the log file to <code>log_beserver.txt.bak</code> . Backup Exec server appends the new log details to <code>log_beserver.txt</code> .

ITEM	DESCRIPTION
	<p>Individual file size = Maximum log file size / Split into</p>
	<p>The number of <code>log_beserver .bak</code> files that Backup Exec server creates depends on the value that is specified in the Split into field.</p>
	<p>For example, if you specify the Maximum log file size as 1 MB and the Split into value as 4, the individual file size is 256 KB. Backup Exec server creates a .bak file each time the individual file size reaches 256 KB and names the file as <code>log_beserver .txt .bak4</code> . When the individual file size again reaches 256 KB, the earlier log file is renamed to <code>log_beserver .txt .bak3</code> and the new log file is named <code>log_beserver .txt .bak4</code> .</p>
	<p>The option Max retention is used with the options Maximum log file size and Retention size . When the Backup Exec server log file reaches the maximum size for a log file, Backup Exec server removes the oldest data in the log file. It determines the amount of data to remove based on the value that is specified in the Retention size field.</p>
	<p>For example, if you specify the Maximum log file size as 5 MB and Retention size as 2 MB, when the Backup Exec server log file reaches the maximum log file size, 3 MB of the oldest data is deleted, and 2 MB of the latest data is retained. You have 3 MB of log file space for future Backup Exec server information.</p>
<p>Maximum log file size</p>	<p>Specifies the maximum size of the log file in megabytes.</p>
	<p>The maximum log file size reflects the total size in megabytes for the number of log files that are specified in the option Split into .</p>

ITEM	DESCRIPTION
Retention size	Displays the amount of data to be retained once the log file reaches the maximum log file size.
	The retention size must be smaller than the size that is specified in Maximum log file size .
Split into	Specifies the number of additional log files to be created when
	the log file size reaches the individual file size.
	Individual file size = Maximum log file size / Split into
Enable log size for Job Engine and Remote Agent for Windows Service	Activates the options that let you set the log sizes for the Backup Exec Job Engine and the Backup Exec Remote Agent for Windows services.
Log size limit mode	Determines the options to take when the log files for the Backup Exec Job Engine and the Backup Exec Remote Agent for Windows service reach their maximum sizes.
	The following choices are available:
	- Rename when the maximum size is reached
	- Max retention
	On selecting the Rename when the maximum size is reached option, when the Backup Exec engine log file, <code>-bengine00.txt</code> , reaches the individual file size, Backup Exec engine renames the log file to <code>-bengine00.bak</code> . Backup Exec engine appends the new log details to <code>-bengine00.txt</code> .
	Individual file size = Maximum log file size / Split into

ITEM	DESCRIPTION
	<p>The number of <code>-bengine00.bak</code> files that Backup Exec engine creates depends on the value that is specified in the Split into field.</p>
	<p>For example, if you specify the Maximum log file size as 1 MB and the Split into value as 4, the individual file size is 256 KB. Backup Exec engine creates a .bak file each time the individual file size reaches 256 KB and names the file as <code>-bengine00.bak4</code> . When the individual file size again reaches 256 KB, the earlier log file is renamed to <code>-bengine00.bak3</code> and the new log file is named <code>-bengine00.bak4</code> .</p>
	<p>The option Max retention is used with the options Maximum log size and Retention size . When the Backup Exec engine log file reaches the maximum size for a log file, Backup Exec removes the oldest data in the log file. It determines the amount of data to remove based on the value that is specified in the Retention size field.</p>
	<p>For example, if you specify the Maximum log file size as 5 MB and Retention size as 2 MB, when the Backup Exec engine log file reaches the maximum log file size, 3 MB of the oldest data is deleted, and 2 MB of the latest data is retained. You have 3 MB of log file space for future Backup Exec engine information.</p>
<p>Maximum log file size</p>	<p>Specifies the maximum size of the log file in megabytes.</p>
<p>Retention size</p>	<p>Displays the amount of data to be retained once the log file reaches the maximum log file size.</p>
	<p>The retention size must be smaller than the size that is specified in Maximum log file size.</p>

ITEM	DESCRIPTION
Split into	Specifies the number of additional log files to be created when
	the log file size reaches the individual file size.
	Individual file size = Maximum log file size / Split into
Set Debug Log Location	Activates the Set Debug Log Location option.
New log location	Indicates the path to the new log folder location you want to use.
	You can enter a path to the folder location you want to use, or you can click Browse to navigate to a desired folder location.

## Setting debug logging and the debug log sizes for Agent for Windows computers

Enable Debug Logs lets you activate and configure various options for log file operations on computers running the Agent for Windows.

See [About Backup Exec Utility general tasks](#).

To set debug logging and debug log sizes for Agent for Windows computers

1. From All Agent for Windows Computers, select a computer that runs the Agent for Windows.
2. In the task pane, under General Tasks, click **Enable Debug Logs**.
3. Set the appropriate options.

See [Debug log options and debug log size options for Agent for Windows computers](#).

1. Click **OK**.

## Debug log options and debug log size options for Agent for Windows computers

You can set the debug log options that you want for Agent for Windows computers.

See [Setting debug logging and the debug log sizes for Agent for Windows computers](#).

**Table: Edit Debug Log Size Configuration for Agent for Windows options**

ITEM	DESCRIPTION
Agent for Windows	Displays the name of the computer that is running the Agent for Windows.
Enable debug log	Lets you enable debug logging on the computer running the Agent for Windows.
NDMP Option debug level	Sets the level of Agent for Windows debugging details that are logged.
	Technical support determines the level to use.
Log NDMP errors only	Provides both general information and the errors that are generated.
Log flow messages	Provides additional information about the activity that occurs and the NDMP errors that are generated.
Verbose Logging	Provides the additional information that you do not get with either of the Log NDMP errors only or Log flow messages options.
Log file append	Appends engine and Agent for Windows NDMP log information to the existing engine and Agent for Windows NDMP log file.
Enable maximum log size	Lets you set the maximum size of the log file in megabytes.
	If you select Rename when the maximum size is reached , the maximum log file size reflects the size in megabytes of all the log files that are created when you select the option Split into .
Log size limit mode	Determines the options you can take when the log file for the Backup Exec remote service reaches its maximum size.
	The following options are available:

ITEM	DESCRIPTION
	- Rename when the maximum size is reached
	- Max retention
	<p>On selecting the Rename when the maximum size is reached option, when the Backup Exec remote log file, <code>-beremote00.txt</code>, reaches the individual file size, Backup Exec remote renames the log file to <code>-beremote00.bak</code>. Backup Exec remote appends the new log details to <code>-beremote00.txt</code>.</p>
	<p>Individual file size = Maximum log file size / Split into</p>
	<p>The number of <code>-beremote00.bak</code> files that Backup Exec remote creates depends on the value that is specified in the Split into field.</p>
	<p>For example, if you specify the Maximum log file size as 1 MB and the Split into value as 4, the individual file size is 256 KB. Backup Exec creates a .bak file each time the individual file size reaches 256 KB and names the file as <code>-beremote00.bak4</code>. When the individual file size again reaches 256 KB, the earlier log file is renamed to <code>-beremote00.bak3</code> and the new log file is named <code>-beremote00.bak1</code>.</p>
	<p>The option Max retention is used with the options Maximum log size and Retention size. When the Backup Exec remote log file reaches the maximum size for a log file, Backup Exec removes the oldest data in the log file. It determines the amount to remove based on the value that is specified in the Retention size field.</p>
	<p>For example, if you specify the Maximum log file size as 5 MB and Retention size as 2 MB, when the Backup Exec remote log file reaches</p>

ITEM	DESCRIPTION
	the maximum log file size, 3 MB of the oldest data is deleted, and 2 MB of the latest data is retained. You have 3 MB of log file space for future Backup Exec server information.
Maximum log file size	Specifies the maximum size of the log file in megabytes.
Retention size	Displays the amount of data to be retained once the log file reaches the maximum log file size.
	The retention size must be smaller than the size that is specified in Maximum log file size .
Split into	Specifies the number of additional log files to be created when
	the log file size reaches the individual file size.
	Individual file size = Maximum log file size / Split into
Set log file location	Lets you set a new folder location in which to store the debug log files.
New log location	Indicates the path to the new log folder location you want to use.
	You can enter a path to the folder location you want to use, or you can click Browse to navigate to a desired folder location.

## Setting the location for the job log and the catalogs

Set Job Log and Catalog Location lets you change job log and catalog locations on a Backup Exec server.

To set the location for the job log and the catalogs

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.

2. In the task pane, under General Tasks, click **Set Job Log and Catalog Location**.
3. Set the appropriate options.

See [Job log and catalog location change options](#).

1. Click **OK**.

### Job log and catalog location change options

Set the job log location and the catalog location on a Backup Exec server.

See [Setting the location for the job log and the catalogs](#).

**Table: Job log and catalog location change options**

ITEM	DESCRIPTION
Backup Exec server	Displays the name of the Backup Exec server for which you want to change job log and catalog storage locations.
Change job log location	Lets you change the storage location of the job log.
Destination job log path	Indicates the path where you want the job logs to be stored.
	You can enter a path to the folder location you want to use, or you can click Browse to navigate to a folder location.
Change catalog location	Lets you change the storage location of the catalogs.
Destination catalog path	Indicates the path where you want the catalogs to be stored.
	You can enter a path to the folder location that you want to use, or you can click Browse to navigate to a folder location.

### Viewing server properties for the Backup Exec server

You can view information about the Backup Exec server, such as the status of the server.

To view server properties for the Backup Exec server

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the results pane, select a Backup Exec server.
3. In the task pane, under General Tasks, click **Backup Exec Server Properties**.
4. Click **Server**.

See [Server properties for a Backup Exec server](#).

1. Click **OK**.

### Server properties for a Backup Exec server

You can view the following server properties for a Backup Exec server.

See [Viewing server properties for the Backup Exec server](#).

**Table: Server properties for a Backup Exec server**

ITEM	DESCRIPTION
Name	Displays the name of the Backup Exec server.
Status	Displays the status of the Backup Exec server.
	The following status types can appear:
	- Running Indicates that all services are running.
	- Pause Indicates that the server is paused. You can pause a Backup Exec server to prevent jobs from running on that server while maintenance activities, such as replacing a tape device, are performed. Active jobs are not affected if they started before the server was paused.
	- Unavailable Indicates that the Backup Exec services are not available. Depending on the thresholds that are set, active jobs either stall, fail, or are recovered.

ITEM	DESCRIPTION
	- Not running Indicates that the Backup Exec server is not online. Services have been stopped.
	If the Central Admin Server Option is installed, additional statuses appear.
Description	Displays a description of the server.
Version	Displays the Backup Exec version and revision information.
Serial #	Displays the license under which Backup Exec is installed. Trial Edition appears if a license was not provided during Backup Exec installation.
Start date and time	Displays the date and time Backup Exec was initially installed and started on the Backup Exec server.
Current date and time	Displays the current date and time.
Number of devices	Displays the number of storage devices that are connected to the Backup Exec server. In systems with attached multi-drive robotic libraries, each drive in the robotic library represents a separate device.
Number of active jobs	Displays the number of jobs that are currently in progress on the Backup Exec server.
Total number of alerts since server startup	Displays the total number of alerts that were generated on this Backup Exec server since the Backup Exec services were last started.

## Viewing a list of licensed and installed options for a Backup Exec server

You can view a list of the Backup Exec options that are installed and licensed on the Backup Exec server.

To view a list of licensed and installed options for a Backup Exec server

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the Results pane, select a Backup Exec server.
3. In the task pane, under General Tasks, click **Backup Exec Server Properties**.
4. Click the Options tab to view the additional options that are licensed and installed on the Backup Exec server.

See [Licensed and installed Backup Exec options on a Backup Exec server](#).

1. Click **OK**.

### Licensed and installed Backup Exec options on a Backup Exec server

The Options tab shows you a list of all licensed and installed Backup Exec options on the Backup Exec server.

See [Viewing a list of licensed and installed options for a Backup Exec server](#).

**Table: Licensed and installed Backup Exec options on a Backup Exec server**

ITEM	DESCRIPTION
Option	Displays the name of the Backup Exec options.
Licensed	Displays the licensed status of an option.
	Licensed statuses include the following:
	- Yes Appears if the option is licensed on the Backup Exec server.
	- No Appears if the option is not licensed.
Installed	Displays the installed status of an option.
	Installed statuses include the following:
	- Yes Appears if the option is installed on the Backup Exec server.
	- No Appears if the option is not installed.

ITEM	DESCRIPTION
	<b>Note:</b> If the option is installed, it may still require additional configuration.
	For configuration details, see the Backup Exec Administrator's Guide .

## Viewing system properties for a Backup Exec server

From the System tab, you can run BE Diagnostics, which is a Backup Exec diagnostic utility. This utility creates a file, `bediag_<computer_name>.txt`, that includes useful configuration information for the server. Technical support can use the results of BE Diagnostics to troubleshoot problems.

To view system properties for a Backup Exec server

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the Results pane, select a Backup Exec server.
3. In the task pane, under General Tasks, click **Backup Exec Server Properties**.
4. Click **System**.

See [System properties for a Backup Exec server](#).

1. Click **OK**.

## System properties for a Backup Exec server

The System tab shows you operating system, processor, and memory details for the Backup Exec server.

See [Viewing system properties for a Backup Exec server](#).

**Table: System properties for a Backup Exec server**

ITEM	DESCRIPTION
Type (Operating System)	Displays the operating system currently running on this Backup Exec server.
Version	Displays the version of the operating system.

ITEM	DESCRIPTION
Build	Displays the build number of the operating system.
Type (Processor)	Displays the processor that is installed in this Backup Exec server.
Level	Displays the level of the processor installed. For example, Pentium IV.
Number of processors	Displays the number of processors on this Backup Exec server.
Physical	Displays the amount of hardware RAM that is installed in the Backup Exec server.
Virtual remaining	Displays the amount of virtual memory remaining on the Backup Exec server.
	See the Backup Exec Administrator's Guide.
Page size	Displays the size of a single virtual memory page.
Page file	Displays the size of the virtual memory paging file.
BE Diagnostics	Runs the BE Diagnostics utility. The results are written to a text file, <code>bediag.txt</code> .
	The text file includes useful configuration information for the computer, such as the following:
	- Account groups, account privileges, and environment settings.
	- Backup Exec software version and registry information, Backup Exec Agent listing, and Windows version information. The text file also gives you SCSI hardware configuration, SQL

ITEM	DESCRIPTION
	Server information, Driver services information, and Windows Services information.
	- File server information, supported shared directories, and Windows sockets information.
	If you call technical support, they may request that you to run BE Diagnostics and provide them with the results. Technical support can use the results of this utility to pinpoint your problem and quickly solve it.

## Managing security certificates

You can view information about the security certificates, and remove the Backup Exec server security certificate and root certificate.

If you delete active certificates by using the Backup Exec Utility, the certificates are regenerated. If you delete expiring certificates, the certificates are not regenerated. If you delete all certificates, they are all regenerated.

### Table: Managing security certificates

ITEM	DESCRIPTION
Backup Exec server	Displays the name of the Backup Exec server to which the security certificate was issued.
Certificate Type	Displays the following certificate types\:
	- Active Root Certificate
	- Active Server Certificate
	- Expiring Root Certificate
	- Expiring Server Certificate
Expiration Date	Displays the date that the security certificate expires.

ITEM	DESCRIPTION
Issued To	Displays the name of the Agent for Windows to which the security certificate was issued.
Issued By	Displays the name of the certificate authority from which the security certificate was issued.

You can remove the security certificate for a Backup Exec server that has established a trust with the Agent for Windows.

#### Removing a security certificate

1. In the Computers pane, click **All Backup Exec Servers**.
2. In the Results pane, select a Backup Exec server.
3. In the task pane, under General Tasks, click **Manage Security Certificates**.
4. Click the certificate that you want to remove, and then click **Remove**.

## About Backup Exec Utility services tasks

Table: Backup Exec Utility services tasks lists Backup Exec Utility services tasks.

Table: Backup Exec Utility services tasks

TASK	DESCRIPTION
<a href="#">Stopping Backup Exec services</a>	Stops the Backup Exec services remotely on any Backup Exec server that appears in the Backup Exec Utility.
<a href="#">Starting Backup Exec services</a>	Starts the Backup Exec services remotely on any Backup Exec server that appears in the Backup Exec Utility.
<a href="#">Changing service accounts</a>	Configures the credentials that comprise the Backup Exec service account.
<a href="#">Editing Backup Exec server configurations</a>	Configures Backup Exec to set automatic responses to several media alerts.

TASK	DESCRIPTION
Moving an existing Backup Exec server	Moves an existing Backup Exec server to a different computer.

## Stopping Backup Exec services

Stop Services lets you stop Backup Exec services remotely on any Backup Exec server that appears in the Backup Exec Utility.

When you stop services on a clustered Backup Exec server, you take the entire Backup Exec cluster group offline. To bring the entire group online again, you must restart the services by using the Start Services option.

See [Starting Backup Exec services](#).

To stop Backup Exec services on a Backup Exec server

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Services Tasks, click **Stop Services**.
3. Click **Yes** to confirm the stop services operation.
4. After the services stop, click **Close**.

## Starting Backup Exec services

Start Services lets you start Backup Exec services remotely on any Backup Exec server that appears in the Backup Exec Utility.

When you start services on a clustered Backup Exec server, you place the entire Backup Exec cluster group online. To bring the entire group offline again, stop the services by using Stop Services.

See [Stopping Backup Exec services](#).

To start Backup Exec services on a Backup Exec server

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Services Tasks, click **Start Services**.
3. After the services start, click **Close**.

## Changing service accounts

Change Service Account lets you reconfigure the credentials that comprise the Backup Exec service account.

Before the new service account configuration can take effect, you must stop and restart the services on the Backup Exec server.

See [Starting Backup Exec services](#).

See [Change service account options](#).

To change a Backup Exec server service account

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.

If you change the service account on a clustered Backup Exec server, you must first bring the Backup Exec cluster group offline. Use Stop Services.

1. In the task pane, under Services Tasks, click **Change Service Account**.
2. Change the account options as appropriate.

See [Change service account options](#).

1. Click **OK**.
2. Click **Close** when the service account changes are completed.

More Information

[Stopping Backup Exec services](#)

## Change service account options

You can reconfigure the credentials that are required for a service account by changing the options the following options.

See [Changing service accounts](#).

**Table: Set Service Account options**

ITEM	DESCRIPTION
Backup Exec Servers	Displays the name of the Backup Exec server on which you want to change the service account.
Account	Indicates the user account that is designated for the Backup Exec services.
	The account must previously exist and be a member of the Administrators or Backup Operators groups.
	The account must also be assigned the following rights on all destination servers:
	- Log on as a service
	- Act as part of the operating system
	- Create a token object
	- Manage auditing and security log
	- Backup files and directories
	- Restore files and directories
Password	Indicates the password that is used to access the service account.
Confirm Password	Confirms the password that you entered in the Password field.
Start type	Lets you change the startup behavior of the service account.
	The following choices are available:
	- Automatic
	- Manual

ITEM	DESCRIPTION
	- Disabled

## Editing Backup Exec server configurations

Edit Configuration lets you configure Backup Exec to set automatic responses to several media alerts. To use this option you must also set the option Automatically clear after on the Backup Exec Alert Configuration dialog box.

See [Edit configuration options](#).

The following media alerts can be configured to use automatic responses:

- Media Overwrite
- Media Remove
- Media Insert
- Library Insert

You can also change the time that is required for a Backup Exec server to release a tape drive before it attempts to acquire another tape drive. In addition, you can also change the amount of time that the Backup Exec server keeps possession of a tape drive after a job completes.

To edit a Backup Exec server configuration

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. On the task pane, under Services Tasks, click **Edit Configuration**.
3. Edit the appropriate options.

See [Edit configuration options](#).

1. Click **OK**.

### Edit configuration options

Edit Configuration lets you configure Backup Exec to set automatic responses to several media alerts. To use this option you must also set the option Automatically clear after on the Backup Exec Alert Configuration dialog box.

See [Editing Backup Exec server configurations](#).

**Table: Edit configuration options**

ITEM	DESCRIPTION
Backup Exec	Displays the name of the Backup Exec server on which you want to change the service account.
Set Defaults	Resets the Backup Exec server configuration to Backup Exec default specifications.
Delay before mount time	Indicates the amount of time the Backup Exec server waits after releasing a tape drive and before attempting to acquire a storage device.
Next job wait time	Indicates the amount of time that the Backup Exec server keeps possession of a storage device after a job completes.
	You can use this option to save time when multiple append jobs are sent to a particular Backup Exec server during the same backup window.
	Increasing the wait time between jobs delays the start of the media dismount sequence. If an append job is sent to the storage device before the allotted time expires, the media dismount sequence is averted. The job then starts immediately.
	If an append job is not sent to the storage device in the allotted time, the media dismount sequence begins. When the job completes, the Backup Exec server releases the storage device.
Mount poll time	Indicates the time interval (in seconds) before Backup Exec does one of the following\:
	- Attempts to mount media to run a job.
	- Attempts to acquire a storage device with media in it.

ITEM	DESCRIPTION
Media Overwrite Alert	Indicates the automated response for the Media Overwrite Alert .
	The following responses are available:
	- Yes or OK
	- No
	- Cancel
Media Remove Alert	Indicates the automated response for the Media Remove Alert .
	The following responses are available:
	- Yes or OK
	- No
	- Cancel
Media Insert Alert	Indicates the automated response for the Media Insert Alert .
	The following responses are available:
	- Yes or OK
	- No
	- Cancel
Library Insert Alert	Indicates the automated response for the Library Insert Alert .
	The following responses are available:
	- Yes or OK
	- No

ITEM	DESCRIPTION
	- Cancel
File system uses asynchronous I/O	Lets Backup Exec use a proprietary method for accessing files (on tape and on hard drive) for both read and write functionality.
	When you select this option, Backup Exec uses a proprietary method to accelerate such operations. When you clear the option, Backup Exec does not accelerate such operations.
	This option negatively affects the performance of Backup Exec tape operations (such as backup, verify, and restore) in an attempt to resolve minor hardware-related errors.
Enable restrict anonymous support	Lets Backup Exec use Microsoft's Restrict Anonymous security feature, which prevents anonymous connectivity to a Windows server.
	This option forces Backup Exec to provide credentials when it connects to a resource.
Use fast file restore	Speeds the process of finding the appropriate spot on the tape that contains the data you want to restore. In some cases there can be problems accessing the tape using Fast File Access. Disabling this feature can work around tape access problems during restores.
Use fast file append	Speeds the process of finding the next usable space on the tape where Backup Exec can append additional data. In some cases there can be problems doing a direct seek to the tape's End of Data marker. You can disable this feature if tape access problems occur during a backup job.

## Moving an existing Backup Exec server

Backup Exec Server Migration Assistant lets you move an existing Backup Exec server to a different computer.

To move an existing Backup Exec server

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Services Tasks, click **Backup Exec Server Migration Assistant**.
3. Follow the instructions that are provided in the document that appears.

## About Backup Exec Utility CASO tasks

Table: Backup Exec Utility CASO tasks lists the Backup Exec Utility CASO tasks.

Table: Backup Exec Utility CASO tasks

TASK	DESCRIPTION
Enabling communications with the managed Backup Exec server	Resumes the communication between the central administration server and a managed Backup Exec server, bringing the managed Backup Exec server online.
Disabling communication with the managed Backup Exec server	Stops the communication between the central administration server and a managed Backup Exec server, thus rendering the managed Backup Exec server unavailable.
Moving a managed Backup Exec server	Moves a managed Backup Exec server to a different central administration server.

## Enabling communications with the managed Backup Exec server

Enable Communications with the Managed Backup Exec Server lets you enable communications between the central administration server and a managed Backup Exec server. This option brings back the managed Backup Exec server online, and makes it available for job delegation.

When you use Enable Communications with the Managed Backup Exec Server, the following occurs:

- The managed Backup Exec server's communications status changes from Disabled to Enabled in the Communications Status column of the Backup Exec server.
- The managed Backup Exec server's status change also appears in the Backup Exec Server Status column, which changes from Unavailable to Online.
- An icon that represents a fully functioning managed Backup Exec server appears next to the icon that represents the managed Backup Exec server.

To enable communications with the managed Backup Exec server

1. Start BEUtility on the central administration server.
2. Select a paused managed Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
3. In the task pane, under CASO Tasks, click **Enable Communications with the Managed Backup Exec Server**.
4. Click **Yes** to confirm the stopping and restarting of the Backup Exec services.
5. When the operation finishes, click **Close**.

## Disabling communication with the managed Backup Exec server

Disable Communications with the Managed Backup Exec Server lets you disable communications between the central administration server and a managed Backup Exec server. The managed Backup Exec server becomes unavailable for job delegation.

When you use Disable Communications with the Managed Backup Exec Server, the following occurs:

- The managed Backup Exec server's communications status changes from Enabled to Disabled in the Communications Status column of the Backup Exec server.
- The managed Backup Exec server's status change also appears in the Backup Exec Server Status column, which changes from Online to Unavailable.
- An icon that represents a disabled managed Backup Exec server appears next to the icon that represents the managed Backup Exec server.

To disable CASO job delegation on a Backup Exec server

1. Start BEUtility on the central administration server.
2. Select a managed Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.

3. On the task pane, under CASO Tasks, click **Disable Communications with the Managed Backup Exec Server**.
4. Click **Yes** to confirm the stopping and restarting of the Backup Exec services.
5. When the operation finishes, click **Close**.

## Moving a managed Backup Exec server

Move Managed Backup Exec Server lets you move a managed media to a different central administration server.

To move a managed Backup Exec server

1. Start BEUtility at the central administration server.
2. Expand All Backup Exec Servers.
3. Select the managed Backup Exec server you want to move to a different central administration server.
4. In the task pane, under CASO Tasks, click **Move Managed Backup Exec Server**.
5. Enter the name of a central administration server to which to move the managed Backup Exec server. You can also click **Browse** to navigate to a central administration server.
6. Click **OK**.
7. On the managed Backup Exec server, stop the Backup Exec services.
8. On the managed Backup Exec server, restart the Backup Exec services.

## About Backup Exec Utility database tasks

You can perform the following Backup Exec Utility tasks on the Backup Exec Database.

You can run database tasks only on a stand-alone server or on a central administration server.

**Table:** [Backup Exec Utility database tasks](#) lists Backup Exec Utility database tasks.

Table: Backup Exec Utility database tasks

TASK	DESCRIPTION
<a href="#">Checking the database consistency</a>	Checks the consistency or validity of the Backup Exec Database.

TASK	DESCRIPTION
Aging the database	Ages the Backup Exec Database by deleting information that is considered old.
Compacting a Backup Exec Database	Reduces the size of the Backup Exec Database by removing the unused space in a database.
Dumping a Backup Exec Database	Backs up the Backup Exec Database to your hard drive.
Rebuilding Backup Exec Database indices	Rebuilds the Backup Exec Database indices in the event the indices become corrupt.
Repairing a Backup Exec Database	Repairs a Backup Exec Database.
Recovering a Backup Exec Database	Recovers a Backup Exec Database.
Changing database access	Grants or revokes a user's Backup Exec Database access.
Changing the Backup Exec database location	Changes the Microsoft SQL Server instance that the Backup Exec Database uses.
Copying a database	Copies an existing Backup Exec Database from a computer using a specific name to another computer that uses the same name.

## Checking the database consistency

Check Database Consistency lets you check the consistency or validity of a Backup Exec database before you back it up. A consistency check enables you to find problems in a database before you back it up.

To check the consistency of a Backup Exec database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. On the task pane, under Database Tasks, click **Check Database Consistency**.
3. After the operation finishes, click **Close**.

## Aging the database

Age Database lets you age a Backup Exec Database by deleting the information that is old. The age of information is based on the aging criteria that you define.

To age a Backup Exec database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Database Tasks, click **Age Database**.
3. After the operation finishes, click **Close**.

## Compacting a Backup Exec Database

Compact Database lets you shrink the database by removing a database's unused space.

To compact a Backup Exec Database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Database Tasks, click **Compact Database**.
3. After the operation finishes, click **Close**.

## Dumping a Backup Exec Database

Dump Database lets you back up the database to your hard drive.

To dump a Backup Exec Database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Database Tasks, click **Dump Database**.
3. After the operation finishes, click **Close**.

## Rebuilding Backup Exec Database indices

Rebuild Indices lets you rebuild Backup Exec Database indices if the indices become corrupt.

To rebuild Backup Exec Database indices

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.

2. In the task pane, under Database Tasks, click **Rebuild Indices**.
3. After the operation finishes, click **Close**.

## Repairing a Backup Exec Database

Repair Database lets you repair a database after you find the problems that may have been uncovered during a database consistency check.

To repair a Backup Exec Database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Database Tasks, click **Repair Database**.
3. After the operation finishes, click **Close**.

## Recovering a Backup Exec Database

Recover Database lets you recover a database that has been lost or corrupted.

To recover a Backup Exec Database

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. On the task pane, under Database Tasks, click **Recover Database**.
3. Select from the following Backup Exec server database recovery options.

See [Recover database options](#).

1. After the operation finishes, click **Close**.

### Recover database options

Recover Database lets you recover a database that has been lost or corrupted.

See [Recovering a Backup Exec Database](#).

**Table: Recover Database options**

ITEM	DESCRIPTION
Backup Exec	Displays the name of the Backup Exec server on which you want to recover the database.

ITEM	DESCRIPTION
Database instance	Indicates the name of the Backup Exec Database that you want to recover. You can perform this operation on only one database at a time.
Use best recovery method for current configuration	Attempts to fix and recover the existing database.
	You can select this option to attempt to fix and recover the existing database.
	However, if the database cannot be fixed, Backup Exec does the following:
	- Deletes the database and then creates a new one.
	- Deletes the database and then recovers it from a previous database dump.
	<p><b>Note:</b> Use this option only under the guidance of Technical Support. The database recovery operation may result in the loss of existing information if there are changes to the blocked items since the last BEDB backup. To ensure that you have the latest blocked items information, it is recommended to back up the BEDB using the dump database option before proceeding with the database recovery operation. Optionally, you can also back up the imported blocked items by running the <code>Export-BEItemsBlockedBEMCLI</code> command and then import the copy of the blocked items using the <code>Import-BEItemsToBlockBEMCLI</code> command, after the operation is complete.</p>
Drop existing database and reload from backup	Deletes the existing database and restores the backup.
	This option works with the Backup Exec option Save contents of database to the Backup Exec

ITEM	DESCRIPTION
	<p>data directory , which you can find in Database Maintenance .</p>
	<p>When you set this option, Backup Exec automatically dumps the database to the Backup Exec server's hard drive at a predetermined schedule that you define. When you run the Backup Exec Utility task Recover Database and you select this option, the existing database is deleted. The database is replaced with the copy of the database that was dumped to the Backup Exec data directory.</p>
	<p><b>Note:</b> Use this option only under the guidance of Technical Support. The database recovery operation may result in the loss of existing information if there are changes to the blocked items since the last BEDB backup. To ensure that you have the latest blocked items information, it is recommended to back up the BEDB using the dump database option before proceeding with the database recovery operation. Optionally, you can also back up the imported blocked items by running theExport-BEItemsBlockedBEMCLI command and then import the copy of the items files using theImport-BEItemsToBlockBEMCLI command, after the operation is complete.</p>
	<p>See the Backup Exec Administrator's Guide .</p>
<p>Drop existing database and reload from base</p>	<p>Deletes the existing database and replaces it with the base database called BEDB_Dat.bak.</p>
	<p>After your initial installation of Backup Exec, a copy of the original, empty production Backup Exec Database is created, named BEDB_Dat.bak. The empty database copy resides in the directory where Backup Exec is installed.</p>

ITEM	DESCRIPTION
	<p><b>Note:</b> This operation deletes the existing database and replaces it with the base database. Backup Exec logon accounts, jobs, media sets, disk storage folders, information about blocked items, encryption keys, and other settings will be discarded. You will have to create or configure all of these items again. Use theDump Databaseoption to back up the database to your hard drive before you use the optionDrop existing database and reload from base. For blocked items, run theExport-BEItemsBlockedBEMCLI command to back up any blocked items. You must import the blocked items using theImport-BEItemsToBlockBEMCLI command after the database recovery operation is complete.</p>
	<p>See <a href="#">Dumping a Backup Exec Database</a> .</p>
	<p>If you roll back the Backup Exec Database and then experience problems restarting the Backup Exec services, a Backup Exec Database schema mismatch may have occurred. You should check the Windows Event Viewer for confirmation. If a schema mismatch occurs, you must re-apply all Backup Exec hotfixes and services packs that were installed on the original production database. This process should resolve the issue.</p>
	<p>Only use this option under the guidance of technical support.</p>

## Changing database access

Change Database Access lets you grant or revoke a user's database access to the Backup Exec Database. Use this option if you change the Backup Exec service account. After you change the service account, you can use Change Database Access to give the new account access to the Backup Exec Database.

To change database access

1. Select a Backup Exec server from either a Backup Exec server group or from All Backup Exec Servers.
2. In the task pane, under Database Tasks, click **Change Database Access**.
3. Enter the appropriate account information, and then select the appropriate access.

See [Change Database Access options](#).

1. Click **OK**.
2. After the operation finishes, click **Close**.

### Change Database Access options

Use the following options to grant access or revoke database access for a user name account.

See [Changing database access](#).

**Table: Change Database Access options**

ITEM	DESCRIPTION
Backup Exec	Displays the name of the Backup Exec server.
User name	Indicates the user name account to which you want to revoke access or grant access.
Domain	Indicates the name of the domain where the user name account is registered.
	To use a local account, you must enter the local computer name in the domain field. Backup Exec Utility uses the local computer name if you leave the field blank.
Grant access	Grants database access to the specified user name account.
Revoke access	Revokes database access to the specified user name account.

## Changing the Backup Exec database location

New Backup Exec Database Location lets you change the Microsoft SQL Server instance that the Backup Exec Database uses. The new location can be on another computer running Microsoft SQL Server, or on the same computer running a different instance of SQL Server.

If you use Backup Exec Utility to change the location of the Backup Exec Database to an unsupported SQL instance, such as SQL Server 2008/2005, the job fails and the Backup Exec services stop. You can only move the Backup Exec Database to one of the following supported instances:

- SQL Server 2005 Service Pack 4 or later
- SQL Server 2008 Service Pack 3 or later

To change the new Backup Exec database location

1. In the task pane, under Database Tasks, click **New Backup Exec Database Location**.
2. Enter a destination SQL Server instance.
3. Click **OK**.
4. Click **Yes** to continue.
5. After the operation completes successfully, click **Close**.

## Copying a database

Copy Database lets you copy an existing Backup Exec Database from a computer using a specific name to another computer using the same name. For example, you can replace a Backup Exec server and use the original Backup Exec server's computer name. After you configure the new computer, you can copy the Backup Exec Database to the new computer.

If you use Copy Database to copy the Backup Exec Database to a computer with a different computer name, some database data is lost.

It is recommended that you use this function only to copy Backup Exec Databases between computers with the same name.

To copy a database

1. In the task pane, under Database Tasks, click **Copy Database**.
2. Enter the appropriate information.
3. See [Copy database options](#).

4. Click **OK**.
5. After the operation completes successfully, click **Close**.

### Copy database options

Set the following options to copy a Backup Exec Database.

See [Copy database options](#).

**Table: Copy Database options**

ITEM	DESCRIPTION
Backup Exec	Displays the name of the Backup Exec server where the Backup Exec Database file and log file are located.
Database File	Indicates the name of the existing Backup Exec Database file from which to copy.
	You can also click Browse to navigate to the location of the Backup Exec Database file.
Database Log File	Indicates the name of an existing Backup Exec Database log file from which you want to copy.
	You can also click Browse to navigate to the location of the Backup Exec Database log file.

## About Backup Exec server group tasks

[Table: Backup Exec server group tasks](#) lists Backup Exec server group tasks.

Table: Backup Exec server group tasks

TASK	DESCRIPTION
<a href="#">Adding a Backup Exec server to a Backup Exec server group</a>	Adds a Backup Exec server to a Backup Exec server group.
<a href="#">Removing a Backup Exec server from a Backup Exec server group</a>	Removes a Backup Exec server from a Backup Exec server group.

TASK	DESCRIPTION
Setting a central administration server for the Backup Exec server group	Sets a Backup Exec server as a central administration server for a group of stand-alone Backup Exec servers that are part of a Backup Exec server group.

## Adding a Backup Exec server to a Backup Exec server group

Add Backup Exec Server lets you add a Backup Exec server to a server group. It does not remove a Backup Exec server from All Backup Exec Servers.

To add a Backup Exec server to a Backup Exec server group

1. Select a Backup Exec server group from Backup Exec Server Groups.
2. In the task pane, under Backup Exec Servers Group Tasks, click **Add Backup Exec Server**.
3. Select the Backup Exec server you want to add.
4. Click **OK**.

## Removing a Backup Exec server from a Backup Exec server group

Remove Backup Exec Server lets you remove a Backup Exec server from a server group. This option does not delete the Backup Exec server from the All Backup Exec Servers node.

To remove a Backup Exec server from a Backup Exec server group

1. Select a Backup Exec server group from Backup Exec Server Groups.
2. In the task pane, under Backup Exec Server Group Tasks, click **Remove Backup Exec Server**.
3. Select a Backup Exec server that you want to remove.
4. Click **OK**.

## Setting a central administration server for the Backup Exec server group

Set Central Administration Server for Group lets you set a central administration server for a group of stand-alone Backup Exec servers that are part of a server group. Before you use this task, you must have the Central Admin Server Option installed on the Backup Exec server that you select to be the central administration server.

If you use this task, the Backup Exec server group must have a group of stand-alone Backup Exec servers and at least one central administration server.

To set the central administration server for a Backup Exec server group

1. Select a Backup Exec server group from Backup Exec Server Groups.
2. In the task pane, under Backup Exec Server Group Tasks, click **Set Central Administration Server for Group**.

A list of stand-alone Backup Exec servers that comprise the Backup Exec server group appears in the Backup Exec servers field.

1. In the Central administration server selection list, select a stand-alone Backup Exec server that you want to configure as the central administration server.
2. Click **OK**.
3. Click **Yes** to confirm the stopping and restarting of the Backup Exec services.
4. Click **Yes** to continue.
5. After the operation successfully completes, click **Close**.

## About configuring columns

BEUtility uses panes to present information to you in a structured and organized manner. Within each pane are columns that specify the type of information that is displayed. You can remove columns that may not interest you.

You can also rearrange the order in which the columns appear.

The position of the column names in the Column Settings dialog box dictates the column's positioning within the pane. For example, column names appearing at the top of the list are positioned on the left side of the pane.

More Information

[Hiding a column](#)

[Displaying a column](#)

[Rearranging columns](#)

[Sorting columns](#)

## Hiding a column

You can hide columns that you do not want to appear.

See [Displaying a column](#).

See [Rearranging columns](#).

See [Sorting columns](#).

To hide a column

1. Right-click any column title on the title bar in the pane where you want column information hidden.
2. Click the column title you want to hide.

## Displaying a column

You can add columns to a pane at any time to display additional information.

See [Hiding a column](#).

See [Rearranging columns](#).

See [Sorting columns](#).

To display a column

1. Right-click any column title on the title bar in the pane where you want a column to appear.
2. Select a column that you want to appear.

## Rearranging columns

You can move columns around so that the most relevant information appears on the left side of the pane.

See [Hiding a column](#).

See [Displaying a column](#).

See [Sorting columns](#).

To rearrange columns

1. Right-click any column title.

2. Click **Configure Columns**.
3. Set column options as appropriate.

See [Column settings options](#).

1. Click **OK**.

## Column settings options

BEUtility uses panes to present information to you in a structured and organized manner. Within each pane are columns that specify the type of information that is displayed. You can remove columns that may not interest you.

See [Rearranging columns](#).

**Table: Column Settings options**

ITEM	DESCRIPTION
Move Up	Moves the column name one column to the left in the pane.
Move Down	Moves the selected column name one column to the right in the pane.
Show	Displays the column name.
Hide	Hides the column name.
Width of selected column (in pixels)	Resizes the width of the column.

## Sorting columns

You can sort information by the column titles that appear in a pane. When you sort on column titles, Backup Exec arranges all of the data that matches the sort criteria together. Backup Exec then displays the information in the pane underneath the column titles. Ascending order lists numbers from smallest to largest and lists letters in alphabetical order. Descending order lists numbers from largest to smallest and lists letters in reverse alphabetical order.

To sort column information

1. Right-click any column title on the pane where you want to sort job information.
2. Click **Multi-Column Sort**.

3. Select the options by which to sort.

See [Sorting column information](#).

1. Click **OK**.

### Sorting column information

You can sort information by the column titles that appear in a pane. When you sort on column titles, Backup Exec arranges all of the data that matches the sort criteria together. Backup Exec then displays the information in the pane underneath the column titles.

See [Sorting columns](#).

**Table: Sort options**

ITEM	DESCRIPTION
Sort by	Lists the column information that is available for sort.
Then by	Refines the sort operation by letting you select additional column information on which to sort.
Ascending	Sorts in ascending order.
Descending	Sorts in descending order.